



Tech Info Library

Omnis: Printing Labels With ImageWriter

This article last reviewed: 18 November 1987

To print labels from Omnis 3 or Omnis 3 Plus to any type of ImageWriter, you must set up the application to override form feeds. (It's not necessary to modify the printer driver.)

1. Go into Report Parameters and change the lines per page from the default value of 66 lpp to 0 lpp.
2. In the report layout, for every record, define the report to have as many lines as you desire on the label (at six lines per inch).
3. When setting label (page) size, make sure the size specified is the same distance from the top of one label to the top of the next.

<None>

Keywords: <None>

=====

This information is from the Apple Technical Information Library.

19960215 11:05:19.00

Tech Info Library Article Number: 1302