



Tech Info Library

Apple II Silentype manual A2L0034/030-0095-00: Errata

Page 11... The procedure for printing a High-Res image doesn't work, since Pascal clears the High-Res buffer when you go to the Filer. We suggest modifying the program as shown below:

```
Program Sprio;

USES Turtlegraphics, Applestuff;
Var angle, distance : integer;
    CH : Char;                                (* added *)

Begin
  angle := 0;
  While not Keypress Do
  Begin
    InitTurtle;
    Pencolor (white);
    For distance := 0 to 99 Do
    Begin
      Move (2 * distance);
      Turn (angle);
    End;
    angle := angle + 5;
  End;
  CH:=CHR (17);                                (* added *)
  Unitwrite (6,CH,1,0,12);                    (* added *)
  Textmode
End.
```

Page 13...The discussion on "Echoing to the screen" assumes that you have already done a PR#1 before you do the T command.

Page 18...The discussion in the last paragraph assumes that you have already done a PR#1 before you do the Q command.

Page 38...Line 4, "for the right margin is 2" should be "for the left margin is 2"

Page 39...Program line 6040 should end with Then Goto 6070
Apple Tech Notes

Keywords: <None>

=====

This information is from the Apple Technical Information Library.

19960215 11:05:19.00

Tech Info Library Article Number: 610